

Re-programming Pro-Streamers Using RS232 Port

In some cases it may be necessary to reprogram units using the RS232 port. In order to do this a number of files are distributed in a zip file format. Within the zip folder are several dos batch files labelled serialx.bat (where x is the comm port number)

To upgrade or reload the firmware attach the streamer unit to a PC comm port using a straight through pin to pin male to female 9 pin RS232 lead.

Select the appropriate serial bat file for the comm port used from the list I.e for comm 1 run serial 1 for comm 3 run serial 3 etc.

If a file does not exist for your comm port open one of the bat files in a text editor and modify as appropriate:

eg for comm 13

serial.bat COM1

would be changed to

serial.bat COM13

Then run the bat file from the extracted directory, when prompted connect the streamer unit to the rs232 lead and power up.